

Launching Mighty Math Carnival from the C-drive

You'll just have to do this once, and the settings will be saved from then on.

1. Put the CD (Mighty Math Carnival) in the CD drive.
2. Launch it.
3. Select "Go" then "Stop", from the main screen. This has to be done rather quickly or "Go" will take you to another screen.
4. Dbl. click "My Computer".
5. Right-click on the Mighty Math Carnival icon, to the word "Open".
6. Right-click on "Count" folder, to the word "Copy".
7. Use the back arrow to get back to the C-drive.
8. Open Program Files and maximize the window.
9. Dbl. click the Edmark folder.
10. Right-click "Mighty Math Carnival Countdown" folder to the word "Paste".
11. Remove the CD once everything finishes copying. You shouldn't need the CD anymore.

When the students launch the program from now on, they may have to select "Go" twice for it to work.

Removing Names from Carnival Math

1. Turn Fool Proof off.
2. Double-click "My Computer", and open the "C" drive.
3. Open the following folders in this order: Program File, Edmark, Mighty Math Carnival, Kids Folder.
4. Delete all folders in this window except "Kid 1". This is the Guest.
5. Close all folders and launch Mighty Math Carnival.
6. Get to the Adult Mode by holding down the keys "Control, Alt, A" (no quotes).
7. From the Users tab, select the name you want to remove.
8. Select "Remove".
9. Deselect "Allow New Users to Add Themselves".
10. Quit.

Carnival Math: Getting to the Adult Mode to Change Printer and Access Settings

1. Launch Carnival Countdown.
2. Select “Go”.
3. Press the keys: Control, Alt, A (the letter) all at once.
4. From the Preferences tab, select “Don’t Allow Saving” if you do not want this option. From this same tab, click the “Off” radio button in the Printer box if you do not want printing.
5. Select the “Grow Slides” tab.
6. Set all sections to “A”, and select “Allow child access to Grow Slides”. This way, students can set their own level of difficulty when they launch the program and not rely on the settings from the previous user.
7. From the “Users” tab, deselect “Allow New Users to Add Themselves”. This will eliminate anyone from entering fictitious names or 4-letter words as the name of a user. It will also prevent them from selecting their own name, but they can always log on as “Guest”.